



SB Connectivity Gräbert Archiv Plus

This manual is for connecting the archival software Gräbert Software + Engineering ArchivPlus
Version 6.4.5

Written By: Rene Weber

Gräbert

SOFTWARE + ENGINEERING


INTRODUCTION


This manual is for connecting the archival software Gräbert Software + Engineering ArchivPlus Version 6.4.5.

This guide is tested with the Silent Brick WORM Archive Version 2.11


Step 1 — General Information

 **Requirements** Compliance Option is necessary to enable various WORM volume types.

 **Installation and Connectors** Installation and electrical connection as well as network connection are to be done as described in the manual Installation

 **Network Adjustments** The network settings are to be adjusted as described in the manual Installation


Step 2 — Volume settings



The image displays two screenshots of the 'Add Sub Volume' dialog box. The left screenshot shows the 'Safe files' tab with the 'Volume type' dropdown set to 'WORM with retention (RWRO triggered)'. The retention settings (Years: 10, Days: 0, Hours: 0, Minutes: 0) are highlighted with a red box. The right screenshot shows the 'Miscellaneous' tab with the 'Do not archive 0-byte files' checkbox checked (highlighted with an orange box) and the 'Prevent renaming of files' checkbox checked (highlighted with a green box).

- Create an archive including WORM and Stage Brick
- Create a sub-volume of type WORM with Retention (RWRO triggered).
- The retention period in years and days must be adopted to the value necessary for the data content being archived
- Select the option 'Prevent renaming of files'
- Select the option 'Do not archive 0-byte files'

Step 3 — Share Settings



- Create a **NFS** share for the previously create volume
- Choose 'Add Client'
- Set the IP address of your ArchivePlus server as 'Single IPv4 Address'

Step 4 — Connect ArchivePlus

- Follow the Gräbert manual for connecting the archive via NFS